



HC VMware Module

WWW.HOSTINGCONTROLLER.COM




In This Deck

- ▶ Introducing HC VMware Module
- ▶ Key Features
- ▶ Service Provider Features
- ▶ End User Features
- ▶ Virtual Machine Controls
- ▶ The Environment
- ▶ System Requirements
- ▶ Installing Hosting Controller
- ▶ HC User Structure
- ▶ Provisioning Virtual Machines

Introducing HC VMware Module

Hosting Controller VMware module simply extends a more powerful web interface to the provisioning of virtual machines in VMware ESXi. With the extra benefits of self-service, ESXi management, central repositories and pre-configured templates, all under one roof, it provides a much fuller services proposition to providers for partitioning their hardware.




Key Features

Self Service



Pre-configured OS
Templates



Central Repository



Modern User
Experience





Service Provider Features

VMware Servers

Add, Edit, Delete, Dedicate and Check Health of VMware servers.

Base OS Management

Choose from a wide range of Windows/Linux base OS types. Edit, Disable, Make a copy of base OS types.

Repository Management

Maintain virtual hard disks (.vmdk) files on a separate central location and fetch these files from the central repository.

OS Templates

Add, Edit, Delete and Inspect Disks of VPS templates.

Public IP Addresses

Add and Delete range of logical public IP addresses to and from the VMware server.

Private IP Addresses

Add and Delete range of logical private IP addresses to and from the VMware server.

Plan Management

Add, Sell, Edit and Delete service plans and composite resources with IaaS (virtualization) resources.



Service Provider Features

Network Information

Indicate settings for external and internal networks.

Data Storage Folder

Specify the logical storage containers for virtual machine files.

VM Import

Import existing virtual machines from the ESXi host.

Summary Email Management

Send out summary emails for the creation, transfer and import of virtual machines.

DVD Drive

Allow DVD drive in media on virtual machines.

API Availability

Integrate with external applications and interfaces through a firm API.



End User Features

VM Creation

Create a virtual machine.

VM Deletion

Delete a virtual machine.

VM Search

Search virtual machine by name.

VM Listing

View list of virtual machines.

VM Details

View virtual machine CPU/memory/storage size.

Change Details

Change virtual machine CPU/memory/storage size.



End User Features

VM State

Start, Pause, Shut down and Reboot virtual machine.

Change Password

Change virtual machine administrator password.

Snapshots

Take virtual machine snapshot and view its date taken. Apply and remove snapshot.

Public IP Assignment

Assign and Delete public IP addresses to and from the virtual machine.

Private IP Assignment

Assign and Delete private IP addresses to and from the virtual machine.




Virtual Machine Controls

Virtual Machine Dashboard

Provisioning / Virtual Machines / **Dashboard**

hctechvm444 Administrator [Change Password]

[Start](#) | [Pause](#) | [Shutdown](#) | [Reboot](#) | [Take Snapshot](#)

| Status | Owner | CPU Cores | RAM Size | VHD Size | Public IP Address |
|----------------------|---------|--|--|--|--|
| Running | hcadmin |  2 Cores |  2048 MB |  50 GB | 192.168.1.240 Click to Change |

Virtual Machine Details

General Properties

Snapshots

Public IP Addresses

OS Template: win2k12

Select Offering: I'll choose my own offering


CPU Cores:

RAM Size (MB):

VHD Size (GB):

[Save](#)

The Environment



* HC installation is not required on the ESXi host. It will communicate remotely with the bare-metal ESXi host.

System Requirements



Software

- Windows 2019/2016/2012/2008 Server with HC10 (This is the control server where HC10 and [VMware-viclient](#) & [VMware-VIX API](#) will be installed).
- HC10 Windows License.
- HC Virtualization Module License.




Hardware

- VMware ESXi compatible server. This is the machine which will be used to provision VPS. However HC software itself will not be installed on this server. Intel Xeon 56xx Series or Intel Xeon 75xx Series. [Click here for Compatibility Details](#).
- Windows 2008/2012/2016 Server with HC10 (This is the control server where HC10 and VMware-viclient & VMware-VIX API will be installed).

Installing Hosting Controller

The installation of HC itself is fairly simple. Just download [HC Primary installer](#) and apply it on the Control Server. Follow a step by step wizard to complete the procedure. To view the installation procedure in detail, see [HC10 Installation Guide](#). HC installation is not required on the ESXi host. It will communicate remotely with the bare-metal ESXi host.

HC User Structure



Provisioning Virtual Machines

Login to Panel



Enable VMware Globally



Add a VMware Server



Add OS Template




Add Public IPs



Create Virtual Machine

Logon to Control Panel



Hosting Controller

Control Panel Login

example-username ←

..... ←

[Forgot your password?](#)

➔ Sign in →

Go to <http://YourIP:8797> to log on to HC10 control panel. Specify user credentials and click **Sign in** to proceed.

Configure Cluster Settings

The screenshot displays the Hosting Controller dashboard. At the top, the 'Hosting Controller' header is visible. The main dashboard area includes a 'Server Status' section with the message 'No configured server found.' To the right, there are several quick links: 'Service Plans', 'Sold Plans', 'Panel Users', 'Staff Members', 'Client Tickets', and 'Messages'. Further right, system information is shown, including 'Version: 10.4.2.25353', 'Theme: Twilight (Default)', and 'Language: English'. Below this is a 'Consumption Stats' section with a line graph. At the bottom of the dashboard, there is a 'Configurations' sidebar on the left and a main menu on the right. The 'Configurations' sidebar has a gear icon and the word 'Configurations' written vertically. The main menu is divided into 'Server Manager' and 'System' sections. Under 'Server Manager', the 'Cluster Settings' option is highlighted with a red box. A red arrow points from this box to the right, towards the text instruction.

Go to **Configurations** screen and then proceed to **Cluster Settings**.

Enable VMware

Manage Cluster Settings

On-premises Cloud Services

Microsoft Exchange

Microsoft SharePoint

Skype for Business

Active Directory

IaaS Computing

Status Enabled

Select Provider(s) Microsoft Hyper-V
 VMware

Allow DVD Drive Enable

Internal Network Enable

Templates Repository

Centralized Repository Enable

Save

Under On-premises tab enable IaaS Computing and define VMware globally.

Add VMware Server

Add Server (On-premises) ×

General Information

Server's Friendly Name

VMware

Server Role(s) in Cluster

Select Server Role

IaaS Computing

Add Server & Configure >

Cancel

Go to **Manage Servers >> Add Server** page to add VMware server. Specify a **Friendly Name** for it and select **Server Role(s) in Cluster**. Click **Add Server & Configure** to proceed.

Provide root User to the ESXi Host

Add Server (On-premises) ×

IaaS Computing

General Settings

Select Provider

VMware

Server Credentials

Server API URL

https://192.168.0.68/sdk

(e.g. https://VMware-Instance-IP/sdk)

Server Fingerprint

(required only for centralized templates repository)

Admin User

root

Password


.....



Check Connectivity

Provide the SDK URL, the root user to the ESXi host and its password. Then check for connectivity.

Provide Server Details



Password: [masked] [lock icon]

[Check Connectivity](#)

Data Storage Folder

Virtual Machines Root: [datastore2]

Network Information

External Network: VM Network

Preferred DNS: 192.168.0.1

Alternate DNS: [empty]

Max. Available Limits

CPU Cores: 999999

RAM Size (GB): 999999

VHD Size (GB): 999999

[Save](#) [Cancel](#)

On successful connection provide rest of the details such as **Data Storage**, **Network Information**, **CPU**, **RAM** and **VHD Size**. Click **Save** to add VMware server.

VMware Server Added

Manage Servers

Server Manager / Servers

Search Server by Friendly Name



+ Add Server

Showing 1 to 1 of 1

Show 20 Records



| Friendly Name | Providers | SSUP Date | Build No. | Status | License Status | Actions |
|---------------|-----------|-----------|--------------|---------|--------------------------|-----------------------|
| VMware | | | 10.7.2.26056 | Running | DEMO (30 days to expire) | Edit Activate License |

VMware Server added successfully.

Add OS Template

Add OS Template

×

| | |
|-----------------------------|---|
| Template Name | <input type="text" value="CentOS7"/> |
| Select Templates Repository | <input type="text" value="VMware"/> |
| Base OS Type | <input type="text" value="Cent OS (64-bit)"/> |
| Default Admin Account | <input type="text" value="root"/> |
| Default Admin Password | <input type="password" value="*****"/>  |
| Confirm Password | <input type="password" value="*****"/>  |
| Public Network Name | <input type="text" value="eth0"/> |
| Private Network Name | <input type="text" value="eth1"/> |
| VHD Location | <input type="text" value="[datastore2]\CentoS7.3-1.21\CentoS7.3-1.21.v"/> <input type="button" value="Browse"/> |

Go to **Virtual Module Conf. >> OS Templates** page to add an OS template. Click **Add OS Template** and fill out all the details. Click **Save** to add a template

OS Template Added

Add OS Template

Success: OS template added successfully.

OS Templates

Virt. Module Conf. / OS Templates

Search OS Template by Name



+ Add OS Template

Showing 1 to 1 of 1

Show 20 Records

| Template Name | Base OS Type | Template Repository | Usage Count | Actions |
|---------------|------------------|---------------------|-------------|---------------------|
| CentOS7 | Cent OS (64-bit) | VMware (N/A) | 0 | Edit Inspect Disk |

OS Template added successfully.

Add IP Addresses

Add Public IP Address



| | | | |
|---|---------------|----|----|
| Select Server | VMware | | |
| IP Address Range | 192.168.1.22 | To | 24 |
| Subnet Mask | 255.255.255.0 | | |
| Default Gateway | 192.168.0.1 | | |
| <input type="button" value="Save"/> <input type="button" value="Cancel"/> | | | |

Go to Virtual Module Conf. >> Public IP Addresses page to specify a range of public IPs. Click Add Public IP Address and specify the IP Address Range, Subnet Mask and Default Gateway. Click Save to add the IPs.

IP Addresses Added

Add Public IP Address

Success: IP address added successfully.

IP Manager (Public IP Address)

Virt. Module Conf. / Public IP Addresses

Search IP Addresses

+ Add Public IP Address

Showing 1 to 3 of 3 Show 20 Records

| IP Address | Subnet Mask | Gateway | Server | Status | Actions |
|--------------|---------------|-------------|--------|--------|---------|
| 192.168.1.22 | 255.255.255.0 | 192.168.0.1 | VMware | Free | Delete |
| 192.168.1.23 | 255.255.255.0 | 192.168.0.1 | VMware | Free | Delete |
| 192.168.1.24 | 255.255.255.0 | 192.168.0.1 | VMware | Free | Delete |

IP Addresses added successfully.

Create Virtual Machine

Create Virtual Machine

Virtual Machine Configurations

Owner Create Virtual Machine for myself

Base OS Type

Select Provider

Select Virtualization Server

Select Offering

CPU Cores

RAM Size (MB)

VHD Size (GB)

Assign Public IP Address Yes

Virtual Machine Details

Virtual Machine Name

Description

Admin Account Administrator name will be shown on details page

Password

Confirm Password

Go to Provisioning >> Virtual Machines page to create a virtual machine. Click **Create Virtual Machine** and specify various configurations such as **Base OS Type**, **CPU**, **RAM**, **VHD** etc. Click **Create Virtual Machine**.

Virtual Machine Created

Virtual Machine Summary ×

Success: Virtual machine creation process started successfully with the following details. ×

Manage Virtual Machines

Provisioning / Virtual Machines

Search Virtual Machine by Name



+ Create Virtual Machine

Showing 1 to 1 of 1

Show 20 Records

| Machine Name | Owner | Provider | Size | Last Known State | Server Name | Actions |
|--------------|---------|----------|-------------------------------|------------------|-------------|------------------|
| CentosVM | hcadmin | | Cores:1, RAM:1024MB, VHD:10GB | Running | VMware | Dashboard Delete |

Virtual machine created successfully.

Contact Hosting Controller



Suite 401, 50 Burnhamthorpe Road W.
Mississauga, ON, L5B 3C2 Canada

Canada: +1 (647) 799-1000

USA: +1 (213) 341-8140

sales@hostingcontroller.com

www.hostingcontroller.com



vmware

